

Probability and Random Processes

Lecture 3

- General measure theory

Measure

- For the generalization of “length” (to Lebesgue measure), we required
 - $\text{length}(A) \geq 0$ for all A
 - $\text{length}(A) = b - a$ if A is an interval with endpoints $a \leq b$
 - $\text{length}(B) = \text{length}(B_1) + \text{length}(B_2)$ if $B = B_1 \cup B_2$ and $B_1 \cap B_2 = \emptyset$
- How to generalize to “measure” in a much more general setting?

- An arbitrary set Ω , and a measure μ on sets from Ω
- As before, require
 - $\mu(A) \geq 0$ for all A
 - $\mu(\emptyset) = 0$
 - $\mu(B) = \mu(B_1) + \mu(B_2)$ if $B = B_1 \cup B_2$ and $B_1 \cap B_2 = \emptyset$ (finite additivity)
- To prove limit theorems and similar, we also need **countable additivity**,
 - for a sequence of sets $\{B_n\}$ with $B_i \cap B_j = \emptyset$ if $i \neq j$

$$\mu \left(\bigcup_n B_n \right) = \sum_n \mu(B_n)$$

- Ω is the universal set (\mathbb{R} in the case of Lebesgue measure), as before we cannot expect that μ can act on all subsets of Ω
 - but sets of the kind $\bigcup_n B_n$ need to be in the domain of μ
- \Rightarrow A **σ -algebra** is a class \mathcal{A} of sets in Ω such that
- $A \in \mathcal{A} \Rightarrow A^c \in \mathcal{A}$
 - $A_n \in \mathcal{A}, n = 1, 2, 3, \dots, \Rightarrow \bigcup_n A_n \in \mathcal{A}$
- On \mathbb{R} , the set \mathcal{L} of Lebesgue measurable sets is a σ -algebra

- A set Ω , a σ -algebra \mathcal{A} of subsets. A **measure** μ is a function $\mu : \mathcal{A} \rightarrow \mathbb{R}^*$ such that
 - $\mu(A) \geq 0$ for all A
 - $\mu(\emptyset) = 0$
 - $\{B_n\}$ with $B_i \cap B_j = \emptyset$ if $i \neq j \Rightarrow$

$$\mu \left(\bigcup_n B_n \right) = \sum_n \mu(B_n)$$

- (Ω, \mathcal{A}) is a **measurable space**, and $(\Omega, \mathcal{A}, \mu)$ is a **measure space**; the sets in \mathcal{A} are called **\mathcal{A} -measurable**

Borel Measurable Sets and Functions

- σ -algebra **generated** by a class \mathcal{C} of sets = smallest σ -algebra that has \mathcal{C} as a subset, notation $\sigma(\mathcal{C})$
- Collection of **Borel sets** $\mathcal{B} = \sigma$ -algebra generated by the class of open sets:
 - In general (beyond \mathbb{R}) the “open sets” are picked from a topology
 - For the real line, \mathcal{B} is the smallest σ -algebra that contains the open intervals
- The sets in \mathcal{B} are called **Borel measurable**
- On the real line, $\mathcal{B} \subset \mathcal{L}$, that is, Borel measurable \Rightarrow Lebesgue measurable (but not vice versa)

- A function $f : \mathcal{U} \rightarrow \mathcal{V}$ is **Borel measurable** if the inverse image of any open set in \mathcal{V} is Borel measurable in \mathcal{U} ,
 - again, “open set” and “Borel measurable” can be general (defined by topologies on \mathcal{U} and \mathcal{V})
- On the real line, let $\mathcal{F} = \{ \text{Borel measurable functions} \}$
 - $f \in \mathcal{F}$ if the inverse image of any open set (or interval) $\subset \mathcal{B}$
 - “Borel measurable set” more general than “open set” \Rightarrow \mathcal{F} contains the continuous functions
 - $f \in \mathcal{F} \Rightarrow f$ Lebesgue measurable (but not vice versa)
 - \mathcal{F} is closed under pointwise limits
 - $\mathcal{F} =$ smallest class of functions that contains the continuous functions and their pointwise limits,
 - c.f. the class $\{ \text{continuous functions} \}$ which is closed under uniform but not pointwise convergence

Some Measure Spaces

- $(\mathbb{R}, \mathcal{L}, \lambda)$ and $(\mathbb{R}, \mathcal{B}, \lambda|_{\mathcal{B}})$
- $\Omega \neq \emptyset$ and $\mathcal{A} = \mathcal{P}(\Omega) =$ set of all subsets. For $A \in \mathcal{A}$, let

$$\mu(A) = \begin{cases} N(A) & A \text{ finite} \\ \infty & A \text{ infinite} \end{cases}$$

where $N(A) =$ number of elements in A ; then μ is called **counting measure**

- $\Omega \neq \emptyset$ and $\mathcal{A} = \mathcal{P}(\Omega)$, for $A \in \mathcal{A}$ the measure

$$\delta_x(A) = \begin{cases} 1 & x \in A \\ 0 & \text{o.w.} \end{cases}$$

is called **Dirac measure** concentrated at x

- A measure space $(\Omega, \mathcal{A}, \mu)$ with the additional condition $\mu(\Omega) = 1$ is called a **probability space** and μ is a **probability measure**
- A measure space $(\Omega, \mathcal{A}, \mu)$. The measure μ is **finite** if $\mu(\Omega) < \infty$.
- Given (Ω, \mathcal{A}) a measure μ is **σ -finite** if there is a sequence $\{A_i\}$, $A_i \in \mathcal{A}$, such that $\cup_i A_i = \Omega$ and $\mu(A_i) < \infty$

Complete Measure

- On the real line: $A \in \mathcal{L}$, $\lambda(A) = 0$ and $B \subset A \Rightarrow B \in \mathcal{L}$, however $A \in \mathcal{B}$, $\lambda|_{\mathcal{B}}(A) = 0$ and $B \subset A$ does in general not imply $B \in \mathcal{B}$
 $\Rightarrow (\mathbb{R}, \mathcal{B}, \lambda|_{\mathcal{B}})$ is not *complete*
- A measure space is **complete** if subsets of sets of measure zero are measurable
- For $(\Omega, \mathcal{A}, \mu)$, let $\bar{\mathcal{A}}$ = collection of all sets of the form $B \cup A$ where $B \in \mathcal{A}$ and $A \subset C$ for some $C \in \mathcal{A}$ with $\mu(C) = 0$. For such a set $\bar{A} = B \cup A \in \bar{\mathcal{A}}$ define $\bar{\mu}(\bar{A}) = \mu(B)$, then
 - $(\Omega, \bar{\mathcal{A}}, \bar{\mu})$ is the **completion** of $(\Omega, \mathcal{A}, \mu)$
 - $\mathcal{A} \subset \bar{\mathcal{A}}$, $\bar{\mu}|_{\mathcal{A}} = \mu$ and $\bar{\mu}(\bar{A}) = \inf\{\mu(A) : \bar{A} \subset A \in \mathcal{A}\}$
 - if $(\Omega, \mathcal{F}, \nu)$ is complete, $\mathcal{A} \subset \mathcal{F}$ and $\nu|_{\mathcal{A}} = \mu$ then $\bar{\mathcal{A}} \subset \mathcal{F}$ and $\nu|_{\bar{\mathcal{A}}} = \bar{\mu}$, i.e. completion gives the smallest complete space
 - the completion is unique if $(\Omega, \mathcal{A}, \mu)$ is σ -finite
- $(\mathbb{R}, \mathcal{L}, \lambda)$ is the completion of $(\mathbb{R}, \mathcal{B}, \lambda|_{\mathcal{B}})$

Measurable Functions

- A measure space $(\Omega, \mathcal{A}, \mu)$
- A function $f : \Omega \rightarrow \mathbb{R}$ is \mathcal{A} -measurable if $f^{-1}(O) \in \mathcal{A}$ for all open sets $O \subset \mathbb{R}$
 - If $(\Omega, \mathcal{A}, \mu)$ is a probability space ($\mu(\Omega) = 1$), then measurable functions are called **random variables**
- Given two measurable spaces (Ω, \mathcal{A}) and (Λ, \mathcal{S}) , a mapping $T : \Omega \rightarrow \Lambda$ is a **measurable transformation** if $T^{-1}(S) \in \mathcal{A}$ for each $S \in \mathcal{S}$ (note: the sets in \mathcal{S} are not necessarily “open”)
- For T from (Ω, \mathcal{A}) to (Λ, \mathcal{S}) ,
 - the class $T^{-1}(\mathcal{S})$ is a σ -algebra $\subset \mathcal{A}$
 - the class $\{L \subset \Lambda : T^{-1}(L) \in \mathcal{A}\}$ is a σ -algebra $\subset \mathcal{S}$
 - if $\mathcal{S} = \sigma(\mathcal{C})$ for some \mathcal{C} , then T is measurable (from \mathcal{A} to \mathcal{S}) iff $T^{-1}(\mathcal{C}) \subset \mathcal{A}$

Almost Everywhere

- A measure space $(\Omega, \mathcal{A}, \mu)$; if a statement is true for elements from all sets in \mathcal{A} except for those in $N \in \mathcal{A}$ with $\mu(N) = 0$, then the statement is true **μ -almost everywhere** (μ -a.e.)
 - ... almost always, for almost all, almost surely, with probability one, almost certainly...
- A sequence $\{f_n\}$ of \mathcal{A} -measurable functions **converges μ -a.e.** to the function f if $\lim_{n \rightarrow \infty} f_n(x) = f$ pointwise for all x except for x in a set $E \in \mathcal{A}$ with $\mu(E) = 0$

Convergence in Measure

- A measure space $(\Omega, \mathcal{A}, \mu)$ and a sequence $\{f_n\}$ of \mathcal{A} -measurable functions. The sequence **converges in measure** to the function f if

$$\lim_{n \rightarrow \infty} \mu(\{x : |f(x) - f_n(x)| \geq \varepsilon\}) = 0$$

for each $\varepsilon > 0$

- If μ is finite then convergence μ -a.e. implies convergence in measure, but not vice versa
- If $(\Omega, \mathcal{A}, \mu)$ is a probability space and $\{f_n\}$ are random variables, then convergence in measure is called convergence **in probability**, and convergence μ -a.e. is **with probability one**